





3D Measurements allow you to visualize and measure on top of your Avatar form and also leave POM (points-of-measure) markers.

To access this tool, click on the  on the 3D window:




- ▶ Select:  to enter the name of the POM, then use CTRL and Click on the Avatar to set the Measurement

*Note- All measurements will require a name to be entered. To exit the 3D Measurements screen the active measurement must be saved.



- ▶ Once the **Magenta Line** appears, the total measurements will be displayed and can be saved as a marker.

- ▶ Using the Circumference Measurement Method is the quickest way to measure around the body. Refine the angle of your POM by utilizing the 3D Gizmo Tool.



- ▶ The Tape Measurement Method allows set markers, such as "Distance from a specific point." You can use this to measure waistband top edges to a specific body landmark for consistent fits.

